Bugs & Wish list

In a file gallery with several pages, the Slideshow should start from the picture displayed on the page | Tiki Wiki CMS Groupware :: Development

In a file gallery with several pages, the Slideshow should start from the picture displayed on the page

Status

Open

Subject

In a file gallery with several pages, the Slideshow should start from the picture displayed on the page

Version

24.x

25.x

26.x

Category

- Feature request
- Developer Training
- Easy for Newbie Dev

Feature

File Gallery (elFinder or standard UI)

Slideshow

Resolution status

New

Submitted by

Bernard Sfez / Tiki Specialist

Keep informed

Adrien

Lastmod by

Bernard Sfez / Tiki Specialist

Rating



Description

On file gallery you have a slideshow option (admin => listing).

Once enabled it will display a slideshow button at the top of gallery pages.

In browse mode you can navigate from page to page:

http://bsfez-11581-7931.show2.tikiwiki.org/tiki-list_file_gallery.php?galleryId=4

When clicking it start a slideshow that display images from the first file in the gallery.

When you have several pages this is not user friendly and is bad UX. (imagine you have hundreds of pictures)

To demonstrate:

- In the edit gallery listing setting I set 2 image per pages (row) to have several pages
- I used small images but bigger images or on mobile the image will cover all the screen (you won't see the screen below the slideshow like in my screenshot)



ADDITIONAL INFORMATION;

Seems that the URL and the slideshow should use an offset parameter but it is not working. Exemple: http://bsfez-11581-7931.show2.tikiwiki.org/tiki-list_file_gallery.php?galleryId=4&offset=4

Solution

Fix: The slide show should start by default using "this" page displayed picture as starting image.

Improvement: When clicking on the slideshow button we should have a sub-choice:

"Start from here"

"Start from the first image"

Importance

5

Easy to solve?

7

Priority

35

Demonstrate Bug (Tiki 19+)

This bug has been demonstrated on show2.tiki.org

Demonstrate Bug (older Tiki versions)

Please demonstrate your bug on show.tikiwiki.org

Version: 18.x ▼

Ticket ID

7931

Created

Thursday 11 November, 2021 05:34:22 GMT-0000 by Bernard Sfez / Tiki Specialist

LastModif

Thursday 11 November, 2021 08:12:33 GMT-0000

Comments



Marc Laporte 09 Feb 23 17:11 GMT-0000

https://gitlab.com/tikiwiki/tiki/-/merge requests/2245

Attachments

filename	created	hits	comment	version	filetype	
----------	---------	------	---------	---------	----------	--

No attachments for this item

The original document is available at https://dev.tiki.org/item 7931-In-a-file-gallery-with-several-pages-the-Slideshow-should-start-from-the-picture-displayed-on-the-page